

Holding down these keys causes the following:

?

#### Pattern Manipulation Hotkeys

- Cntrl + Click&Drag allows you to PAN the graph area.
- Z + Click&Drag causes ZOOM. You can also use your mouse wheel to ZOOM.
- R + Click&Drag causes pattern/pass ROTATION.
- M + Click&Drag causes pattern/pass MAGNIFICATION.
- SHIFT + Click&Drag causes pattern/pass location SHIFTING.
- Delete Key - Deletes the selected Pattern or Pass (depends on whether mode is PATTERNS or PASS)
- Insert Key - Inserts the selected pattern into the selected pass.
- PageUp - Causes the selected pattern to be moved up in the pattern list for the selected pass.
- PageDown - Causes the selected pattern to be moved down in the pattern list for the selected pass.
- Cntrl + Z - Functions the same as the "UNDO" button
- Cntrl + P - Toggles between PASS and PATTERN mode.
- Cntrl + E - Same as clicking the "Create File from Pass" button.
- Right-clicking your mouse calls up further options. Options depend on whether mode is PATTERNS or PASS. *In PATTERN mode you must have the pattern highlighted with the yellow dotted rectangle before you can right-click to access the PATTERN options.*

#### Light Table hotkeys

- I changes whether the light table image should be shown or not (Toggle action).
- P + Click&Drag causes PAN of the light table image.
- Ctrl+V causes the Window's clipboard to be pasted into the light table.

#### Draw Mode Hotkeys

- X allows you to draw straight lines.
- Delete Key - Deletes the last draw point you entered.
- Insert Key - Inserts a draw point at your mouse position.
- Right-clicking your mouse calls up a draw mode editing menu.
- Delete Key while editing draw points causes deletion of the selected draw point.
- Insert Key while editing draw points inserts a draw point between the select draw point and the next draw point.

#### Miscellaneous Hotkeys


- G allows the guidelines to be moved.
- D causes a measurement box to appear for determining spacing and angles. Click your mouse to set the start-point for your measurement.
- Cntrl + S - Saves everything as a PQD file.

Done

- P Key - causes a toggle declaration of the point as a PAUSE.
- J Key - causes a toggle declaration of the point as a JUMP.
- D Key - causes a measurement box to appear for determining spacing and angles. Click your mouse to set the start-point for your measurement.
- Delete Key - causes deletion of one or multiple points.
- Insert Key - Adds a single point at the cursor position.
- Cntrl + Z - causes an UNDO of the last action
- Up, Down, Left & Right Arrows - allows you to move individual points.  
(Hint...Hold down the Cntrl Key to move larger distances)
- Page Up & Page Down - allows you to scroll thru your pattern.  
(Hint...Hold down the Cntrl Key to scroll faster)
- S+Click&Drag - allows the SELECTION of multiple points.
- Pressing the S key twice selects an entire segment of points.


?

OK




### Editor Right-click Menu

Available when multiple pattern points are selected.




### Editor Right-click Menu

Available when a single point is selected  
**IMPORTANT - THIS "REPLACES" THE POPUP ASKING YOU IF YOU WANT TO ELIMINATE REDUNDANT JUMPS.**




### Pass Right-click Menu

Available when in Pass Mode.



### Draw Right-click Menu

Available when in Drawing Mode.



### Multi Pass Right-click Menu

Only available when multiple passes have been selected. Select multiple passes by holding down the 'S' key and clicking on the desired passes. If you are merging passes, select the one you want to merge into FIRST.



### Pattern Right-click Menu

Available when in Pattern Mode - note that yellow dotted box must appear around pattern for this menu to open. Use the SHIFT key to select the pattern and hold down the SHIFT key if necessary to keep the box in displayed.